



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=44H, AL=09H

Version

3.1 and higher

Brief

CHECK IF BLOCK DEVICE REMOTE

Family API

Input

AX = 4409h
BL = drive number (00h = default, 01h = A:, etc)

Return

CF clear if successful

DX = device attribute word
bit 15: drive is SUBSTituted
bit 13: (DR DOS 3.41/5.0 local drives only) always set
media ID needed
bit 12: drive is remote
bit 9: direct I/O not allowed
CF set on error
AX = error code (01h,0Fh,15h) (see #01680 at AH=59h/BX=0000h)

Macro

Notes

on local drives, DX bits not listed above are the attribute word from the device driver header (see #01646 at AH=52h); for remote drives, the other bits appear to be undefined for MS-DOS versions prior to 5.0 (they are all cleared in DOS 5+)

checking whether DX=0800h on return appears to be a fairly reliable method for detecting Microsoft's RAMDRIVE, though not for other ramdisks (there appears to be no simple yet foolproof method for detecting ramdisks, although the presence of only a single copy of the FAT and only a single head on non-removable devices is a fairly good indicator); for Windows95, RAMDRIVE returns DX=4800h

for non-existent remote drives, this function sometimes returns AX=0015h (drive not ready) instead of AX=000Fh (invalid drive) on the first call; a subsequent call will return the correct error code

this function was not supported by Digital Research's DOS Plus

See also

AX=4400h, AX=4408h, AX=440Ah, INT 2F/AX=122Bh

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H, INT 21H : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, INT 21H : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, INT 21H : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, INT 21H : 3300H, 3301H, 3302H
Memory manager	INT 21H : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	INT 21H : 2AH, 2BH, 2CH, 2DH
Misc	INT 21H : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	INT 21H : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H

DOS API	
Devices	INT 21H: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	INT 21H: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @CIs
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

Last update: 2021/05/01
12:56

en:docs:dos:api:int21:44:09 <http://osfree.org/doku/doku.php?id=en:docs:dos:api:int21:44:09&rev=1619873815>

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:

<http://osfree.org/doku/> - **osFree wiki**

Permanent link:

<http://osfree.org/doku/doku.php?id=en:docs:dos:api:int21:44:09&rev=1619873815>

Last update: **2021/05/01 12:56**

