



Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.

2018/09/07 05:04 · prokushev · [0 Comments](#)

Int 21H, AH=00H

Version

1 and higher

Brief

TERMINATE PROGRAM

Family API

[DosExit](#)

Input

```
AH = 00h
CS = PSP segment
```

Return

never returns

Macro

```
INCLUDE DOS.INC

TERMINATE_PROGRAM
```

Notes

This function is obsolete. Use [AH=INT 21/AH=4Ch](#) instead. This function sets the program's return code (ERRORLEVEL) to 00h. Execution continues at the address stored in INT 22 after DOS performs whatever cleanup it needs to do (restoring the INT 22,INT 23,INT 24 vectors from the PSP assumed to be located at offset 0000h in the segment indicated by the stack copy of CS, etc.). If the PSP is its own parent, the process's memory is not freed; if INT 22 additionally points into the terminating program, the process is effectively NOT terminated. Not supported by MS Windows 3.0 DOSX.EXE DOS extender

See also

[AH=4CH](#), [AH=26H](#), [AH=31H](#), [INT 20](#)

Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H , INT 21H : 00H , 25H , 26H , 31H , 34H , 35H , 4BH , 4CH , 4DH , 50H , 51H , 52H , 55H , 62H , INT 22H , INT 27H , INT 28H
File manager	INT 25H , INT 26H , INT 21H : 0DH , 0EH , 0FH , 10H , 11H , 12H , 13H , 14H , 15H , 16H , 17H , 19H , 1AH , 1BH , 1CH , 21H , 22H , 23H , 24H , 27H , 28H , 29H , 2EH , 2FH , 32H , 3305H , 36H , 39H , 3AH , 3BH , 3CH , 3DH , 3EH , 3FH , 40H , 41H , 42H , 4300H , 4301H , 45H , 46H , 4EH , 4FH , 54H , 56H , 5700H , 5701H , 5AH , 5BH , 5c00H , 5c01H , 60H , 67H , 68H , 6900H , 6901H , 6AH , 6CH
Character Device I/O	INT 29H , INT 21H : 01H , 02H , 03H , 04H , 05H , 06H , 07H , 08H , 09H , 0AH , 0BH , 0AH , 0CH , 5D07H , 5D08H , 5D09H , 5D0AH
Signals	INT 23H , INT 24H , INT 21H : 3300H , 3301H , 3302H
Memory manager	INT 21H : 48H , 49H , 4AH , 5800H , 5801H , 5802H , 5803H
Date and Time	INT 21H : 2AH , 2BH , 2CH , 2DH
Misc	INT 21H : 30H , 3306H , 3700H , 3701H , 3702H , 3703H , 59H
NLS	INT 21H : 3303H , 3304H , 3800H , 3801H , 6300H , 6301H , 6301H , 6500H , 6501H , 6502H , 6503H , 6504H , 6505H , 6506H , 6507H , 6520H , 6521H , 6522H , 6523H , 65A0H , 65A1H , 65A2H , 6601H , 6602H
Devices	INT 21H : 4400H , 4401H , 4402H , 4403H , 4404H , 4405H , 4406H , 4407H , 4408H , 4409H , 440AH , 440BH , 440CH , 440DH , 440EH , 440FH , 4410H , 4411H , 53H
Network	INT 21H : 5E00H , 5E01H , 5E02H , 5E03H , 5E04H , 5E05H , 5F00H , 5F01H , 5F02H , 5F03H , 5F04H , 5F05H , 5F07H , 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus

osFree Macro Library	
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments

2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://osfree.org/doku/doku.php?id=en:docs:dos:api:int21:00&rev=1607406678>Last update: **2020/12/08 05:51**