2025/11/12 18:22 1/3 DOSKRNL



Note: This API call is for DOS and Win16 personality only. Use Family API for portability.

2018/09/07 05:04 · prokushev · 0 Comments

# **DOSKRNL**

DOSKRNL is a specialized FreeDOS kernel changed to support DOS in MVM. Mostly all FAT code removed as well as CONFIG.SYS parser. So it smaller in compare with original FreeDOS kernel. Also image format changed because different load logic.

## **Initialization**

DOSKRNL loaded at address differ from standard DOS 0060:0000 address. osFree DOSKRNL expect unknown load address, but in low address of conventional memory.

On DOSKRNL startup registers are following:

- CS:IP starting point
- SS:BP pointer to the DOSKRNL init structure
- SS:SP stack pointer (size around 800 bytes)

#### DOSKRNL init structure:

Offset	Size	Description	
0	2	First free segment after DOSKRNL	
2	2	Size of memory - first free segment (paragraphs)	
4	2	Size of init area (paragraphs)	
6	2	Value of BREAK setting	
8	2	Value of DOS setting	
10	4	Far pointer to list of DOS DEVICE setting	
14	4	Far pointer to SHELL (filepath only)	
18	4	Far pointer to SHELL (arguments)	
22	4	Far pointer to linked list of VDD	
26	1	Current drive (1-A, 2-B, 3-C,)	
27	1	Boot drive (1-A, 2-B, 3-C,)	
????	???	????	

DEVICES is ASCIIZ string with list of DOS devices to be loaded divided by 0AH

SHELL is ASCIIZ string.

SHELL arguments is ASCIIZ string (first byte is as string length, string ends with 0dh)

VDD is linked list of structures:

VDDs linked list (in init area) in standard DOS Device drivers format

offset	Size	Description		
0	4	Pointer to next device (Must be set to -1 for last device)		
4	2	Attributes		
		Bit 15 = 1 if char device 0 if blk		
		if bit 15 is 1		
		Bit 0 = 1 if Current STDIN device		
		Bit 1 = 1 if Current STDOUT output		
		Bit 2 = 1 if Current NULL device		
		Bit 3 = 1 if Current CLOCK device		
		Bit 4 = 1 if SPECIAL		
		Bit 14 is the IOCTL bit		
		Bit 13 is the NON IBM FORMAT bit		
6	2	Pointer to Device strategy entry point		
8	2	Pointer to Device interrupt entry point		
10	8	character device name field. Character devices set a device name. For block devices the first byte is the number of units		

#### Memory map on DOSKRNL start:

Init area	[BP+0+BP+2-BP+4]:0
Free	[BP+0]:0
DOSKRNL	???:0
some data	???
CMOS Data	40:0
Interrupt vectors	0:0

As in most DOS kernels, DOSKRNL moves initialization code to higher conventional memory. But uses init structure, not BIOS INT 12h, for memory information.

DOSKRNL search and initialize XMS driver and moves some parts to HMA. Most other initialization things is same. DOSKRNL initializes standard device drivers and adds and initializes VDDs, passed via init structure. Some things (at least COMMAND.COM, device drivers) also passed via init structure. not CONFIG.SYS. At the present time interface not investigated well.

## **CONFIG.SYS**

CONFIG.SYS device information and some other settings not parsed by DOSKRNL, but passed via init structure. Here list of DOSKRNL options:

- RMSIZE
- DEVICE
- SHELL
- DOS
- BREAK

todo add more info here

https://osfree.org/doku/ Printed on 2025/11/12 18:22

2025/11/12 18:22 3/3 DOSKRNL

Also most of these setting can be adjusted via DOS Properties (aka DOS Settings). Refer OS/2 Version 2.0 Volume 2: DOS and Windows Environment for more information.

## **API**

According different sources IBM DOSKRNL implements API on level of MS-DOS 5.x. osFree DOSKRNL supports API as in FreeDOS kernel. More information about implemented functions available here. DOSKRNL also implements some extensions to API mostly aimed to communicate with host system.

# **Supervisor calls**

DOSKRNL uses SVC interface to call host functions.

From:

https://osfree.org/doku/ - osFree wiki

Permanent link:

https://osfree.org/doku/doku.php?id=en:docs:kernel:doskrnl&rev=1702522663

Last update: **2023/12/14 02:57** 

