



**Note: This API call is for DOS and Win16 personality only. Use [Family API](#) for portability.**

2018/09/07 05:04 · prokushev · [0 Comments](#)

# Int 21H, AH=3CH

## Version

2 and higher

## Brief

“CREAT” - CREATE OR TRUNCATE FILE

## Family API

[DosOpen](#)

## Input

```
AH = 3Ch
CX = file attributes (see #01401)
DS:DX -> ASCIZ filename
```

## Return

```
CF clear if successful
    AX = file handle
CF set on error
    AX = error code (03h,04h,05h) (see #01680 at AH=59h/BX=0000h)
```

## Notes

if a file with the given name exists, it is truncated to zero length

under the FlashTek X-32 DOS extender, the pointer is in DS:EDX

DR DOS checks the system password or explicitly supplied password at the end of the filename against the reserved field in the directory entry before allowing access

Bitfields for file attributes:

Bit(s)	Description
0	read-only
1	hidden
2	system
3	volume label (ignored)
4	reserved, must be zero (directory)
5	archive bit
7	if set, file is shareable under Novell NetWare

## See also

AH=16h,AH=3Dh,AH=5Ah,AH=5Bh,AH=93h,INT 2F/AX=1117h

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

DOS API	
Process manager	INT 20H, <b>INT 21H</b> : 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, <b>INT 21H</b> : 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, <b>INT 21H</b> : 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, <b>INT 21H</b> : 3300H, 3301H, 3302H
Memory manager	<b>INT 21H</b> : 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	<b>INT 21H</b> : 2AH, 2BH, 2CH, 2DH
Misc	<b>INT 21H</b> : 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	<b>INT 21H</b> : 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	<b>INT 21H</b> : 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H
Network	<b>INT 21H</b> : 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H

**osFree Macro Library**

Video I/O	<a href="#">@SetMode</a> <a href="#">@SetCurSz</a> <a href="#">@SetCurPos</a> <a href="#">@GetCur</a> <a href="#">@SetPage</a> <a href="#">@ScrollUp</a> <a href="#">@ScrollDn</a> <a href="#">@Scroll</a> <a href="#">@GetChAtr</a> <a href="#">@PutChAtr</a> <a href="#">@PutCh</a> <a href="#">@SetPalet</a> <a href="#">@SetColor</a> <a href="#">@SetDot</a> <a href="#">@GetDot</a> <a href="#">@WrtTTY</a> <a href="#">@VideoState</a> <a href="#">@GetMode</a> <a href="#">@GetDisplay</a> <a href="#">@GetVideoState</a> <a href="#">@GetEGAInfo</a> <a href="#">@Cls</a>
Hardware info	<a href="#">@Equipment</a> <a href="#">@MemSize</a>
Serial I/O	<a href="#">@AuxInit</a> <a href="#">@AuxSendChar</a> <a href="#">@AuxRecieveChar</a> <a href="#">@AuxStatus</a>
Tape I/O	<a href="#">@TapeOn</a> <a href="#">@TapeOff</a> <a href="#">@TapeRead</a> <a href="#">@TapeWrite</a>
Keyboard I/O	<a href="#">@KbdStatus</a> <a href="#">@CharIn</a> <a href="#">@CharPeek</a>
Printer I/O	<a href="#">@PrnPrint</a> <a href="#">@PrnInit</a> <a href="#">@PrnStatus</a>
Disk I/O	<a href="#">@DskReset</a> <a href="#">@DskStatus</a> <a href="#">@DskRead</a> <a href="#">@DskWrite</a> <a href="#">@DskVerify</a> <a href="#">@DskFormat</a>
Date and Time	<a href="#">@SetTime</a> <a href="#">@GetTime</a>
Mouse	<a href="#">@MouInit</a> <a href="#">@MouShowPointer</a> <a href="#">@MouStatus</a> <a href="#">@MouSetPos</a> <a href="#">@MouSetMickey</a> <a href="#">@MouRegion</a>
Memory manager	<a href="#">@ModBlok</a> <a href="#">SET_BLOCK</a>

2022/10/04 14:28 · [prokushev](#) · [0 Comments](#)2018/09/04 17:23 · [prokushev](#) · [0 Comments](#)**Family API**

DOS	Process Manager	<a href="#">DosBeep</a> <a href="#">DosExit</a> <a href="#">DosSleep</a> <a href="#">DosExecPgm</a>
	File Manager	<a href="#">DosChDir</a> <a href="#">DosChgFilePtr</a> <a href="#">DosClose</a> <a href="#">DosDelete</a> <a href="#">DosDupHandle</a> <a href="#">DosMkDir</a> <a href="#">DosMove</a> <a href="#">DosQCurDir</a> <a href="#">DosQCurDisk</a> <a href="#">DosSetFileMode</a> <a href="#">DosOpen</a> <a href="#">DosQFileInfo</a> <a href="#">DosRead</a> <a href="#">DosQFileMode</a> <a href="#">DosQFSInfo</a> <a href="#">DosQVerify</a> <a href="#">DosRmdir</a> <a href="#">DosSelectDisk</a> <a href="#">DosFindClose</a> <a href="#">DosFindFirst</a> <a href="#">DosFindNext</a> <a href="#">DosSetFileInfo</a> <a href="#">DosSetVerify</a> <a href="#">DosWrite</a> <a href="#">DosFileLocks</a> <a href="#">DosSetFHandState</a> <a href="#">DosNewSize</a> <a href="#">DosBufReset</a> <a href="#">DosQFHandState</a> <a href="#">DosSetFSinfo</a> <a href="#">DosShutdown</a>
	Memory Manager	<a href="#">DosFreeSeg</a> <a href="#">DosSubAlloc</a> <a href="#">DosSubFree</a> <a href="#">DosSubSet</a> <a href="#">DosAllocHuge</a> <a href="#">DosAllocSeg</a> <a href="#">DosReallocHuge</a> <a href="#">DosReallocSeg</a> <a href="#">DosGetHugeShift</a> <a href="#">DosCreateCSAlias</a>
	NLS	<a href="#">DosCaseMap</a> <a href="#">DosGetCtryInfo</a> <a href="#">DosGetDBCSEv</a> <a href="#">DosSetCtryCode</a> <a href="#">DosGetCollate</a> <a href="#">DosGetMessage</a> <a href="#">DosInsMessage</a> <a href="#">DosPutMessage</a>
	Date and Time	<a href="#">DosSetDateTime</a> <a href="#">DosGetDateTime</a>
	Devices	<a href="#">DosDevConfig</a> <a href="#">DosDevIOct1</a> <a href="#">DosDevIOct2</a>
	Signals	<a href="#">DosHoldSignal</a> <a href="#">DosSetSigHandler</a>
	Misc	<a href="#">BadDynLink</a> <a href="#">DosGetEnv</a> <a href="#">DosGetMachineMode</a> <a href="#">DosGetVersion</a> <a href="#">DosError</a> <a href="#">DosErrClass</a> <a href="#">DosSetVec</a>
KBD		<a href="#">KbdCharIn</a> <a href="#">KbdFlushBuffer</a> <a href="#">KbdGetStatus</a> <a href="#">KbdSetStatus</a> <a href="#">KbdStringIn</a> <a href="#">KbdPeek</a>
VIO		<a href="#">VioGetBuf</a> <a href="#">VioGetConfig</a> <a href="#">VioGetCurPos</a> <a href="#">VioGetCurType</a> <a href="#">VioGetPhysBuf</a> <a href="#">VioReadCellStr</a> <a href="#">VioReadCharStr</a> <a href="#">VioScrollUp</a> <a href="#">VioScrollDn</a> <a href="#">VioScrollLf</a> <a href="#">VioScrollRt</a> <a href="#">VioScrUnLock</a> <a href="#">VioSetCurPos</a> <a href="#">VioSetCurType</a> <a href="#">VioSetMode</a> <a href="#">VioGetMode</a> <a href="#">VioShowBuf</a> <a href="#">VioWrtCellStr</a> <a href="#">VioWrtCharStr</a> <a href="#">VioWrtCharStrAtt</a> <a href="#">VioWrtNAttr</a> <a href="#">VioWrtNCell</a> <a href="#">VioWrtNChar</a> <a href="#">VioWrtTTY</a> <a href="#">VioScrLock</a> <a href="#">VioPopUp</a>
Tools		<a href="#">BIND</a>
Modules		<a href="#">DOSCALLS.DLL</a> <a href="#">VIOCALLS.DLL</a> <a href="#">KBDCALLS.DLL</a> <a href="#">MSG.DLL</a>
Libraries		<a href="#">API.LIB</a> <a href="#">OS2386.LIB</a> <a href="#">FAPI.LIB</a> <a href="#">DOSCALLS.LIB</a> <a href="#">SUBCALLS.LIB</a>

2018/08/25 15:05 · [prokushev](#) · [0 Comments](#)

From:

<https://osfree.org/doku/> - **osFree wiki**

Permanent link:

<https://osfree.org/doku/doku.php?id=en:docs:dos:api:int21:3c&rev=1632910422>

Last update: **2021/09/29 10:13**

