Note: This API call is for DOS and Win16 personality only. Use Family API for portability.

2018/09/07 05:04 · prokushev · 0 Comments

Int 21H, AH=1CH

Version

1 and higher

Brief

GET DRIVE PARAMETER BLOCK FOR DEFAULT DRIVE

Family API

Input

```
AH = 1Fh
```

Return

AL = sectors per cluster (allocation unit), or FFh if invalid drive

```
CX = bytes per sector
DX = total number of clusters
DS:BX -> media ID byte (see #01356)
```

Notes

this call was undocumented prior to the release of DOS 5.0; however, only the DOS 4.0+ version of the DPB has been documented

Format of DOS 1.1 and MS-DOS 1.25 drive parameter block:

Offset	Size	Description
00h	BYTE	sequential device ID
01h	BYTE	logical drive number (0=A:)
02h	WORD	bytes per sector
04h	BYTE	highest sector number within a cluster
05h	BYTE	shift count to convert clusters into sectors
06h	WORD	starting sector number of first FAT
08h	BYTE	number of copies of FAT
09h	WORD	number of directory entries
0Bh	WORD	number of first data sector
0Dh	WORD	highest cluster number (number of data clusters + 1)
0Fh	BYTE	sectors per FAT
10h	WORD	starting sector of directory
12h	WORD	address of allocation table

Note: the DOS 1.0 table is the same except that the first and last fields are missing; see INT 21/AH=32h for the DOS 2+ version

See also

SeeAlso: AH=32h,AX=7302h

Note

Text based on Ralf Brown Interrupt List Release 61

DOS API	
Process manager	INT 20H, **INT 21H**: 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H
File manager	INT 25H, INT 26H, **INT 21H**: 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH
Character Device I/O	INT 29H, **INT 21H**: 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH
Signals	INT 23H, INT 24H, **INT 21H**: 3300H, 3301H, 3302H
Memory manager	**INT 21H**: 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H
Date and Time	**INT 21H**: 2AH, 2BH, 2CH, 2DH
Misc	**INT 21H**: 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H
NLS	**INT 21H**: 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H
Devices	**INT 21H**: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H

DOS API	
Network	**INT 21H**: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H
osFree Macro Library	
Video I/O	@SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls
Hardware info	@Equipment @MemSize
Serial I/O	@AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus
Tape I/O	@TapeOn @TapeOff @TapeRead @TapeWrite
Keyboard I/O	@KbdStatus @CharIn @CharPeek
Printer I/O	@PrnPrint @PrnInit @PrnStatus
Disk I/O	@DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat
Date and Time	@SetTime @GetTime
Mouse	@MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion
Memory manager	@ModBlok SET_BLOCK

2022/10/04 14:28 · prokushev · 0 Comments
2018/09/04 17:23 · prokushev · 0 Comments

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOCtl DosDevIOCtl2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek
VIO		VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp
Tools		BIND
Modules		DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL
Libraries		API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB

2018/08/25 15:05 · prokushev · 0 Comments

From:
https://osfree.org/doku/ - **osFree wiki**

Permanent link:
https://osfree.org/doku/doku.php?id=en:docs:dos:api:int21:1f

Last update: **2024/05/02 02:54**