

This call writes a character string to the display starting at the current cursor position.

At the completion of the write, the cursor is positioned at the first position beyond the end of the string.

### Syntax

VioWrtTTY (CharStr, Length, VioHandle)

### Parameters

;CharStr (**PCH**) - input : Address of the string to be written. ;Length (**USHORT**) - input : Length of the character string in bytes. ;VioHandle (**HVIO**) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

### Return Code

rc (USHORT) - return Return code descriptions are: \* 0 NO\_ERROR \* 355 ERROR\_VIO\_MODE \* 436 ERROR\_VIO\_INVALID\_HANDLE \* 465 ERROR\_VIO\_DETACHED

### Remarks

If a string write gets to the end of the line and is not complete, the string write continues at the beginning of the next line. If the write gets to the end of the screen, the screen is scrolled, and the write continues until completed.

The characters carriage return, line feed, backspace, tab, and bell are treated as commands rather than printable characters. Backspace is a non-destructive backspace. Tabs are expanded to provide standard 8-byte-wide fields. VioWrtTTY is the only video call affected by Ctrl-PrtSc and ANSI.

Characters are written using the current attribute defined by ANSI or the default value 7.

VioWrtTTY is supported in graphics mode to process ANSI sequences. This allows the application to enter and exit a graphics mode.

### PM Considerations

Write a character string from the current cursor position in TTY mode to the Advanced VIO presentation space. The cursor is positioned after the last character written at the end of the write.

### Bindings

## C Binding

```
<PRE> #define INCL_VIO

USHORT rc = VioWrtTTY(CharStr, Length, VioHandle);

PCH CharStr; /* String to be written */ USHORT Length; /* Length of string */ HVIO VioHandle; /* Video handle */

USHORT rc; /* return code */ </PRE>
```

## MASM Binding

```
<PRE> EXTRN VioWrtTTY:FAR INCL_VIO EQU 1

PUSH@ OTHER CharStr ;String to be written PUSH WORD Length ;Length of string PUSH WORD VioHandle ;Video handle CALL VioWrtTTY

Returns WORD </PRE>
```

# Note

Text based on [http://www.edm2.com/index.php/VioWrtTTY\\_\(FAPI\)](http://www.edm2.com/index.php/VioWrtTTY_(FAPI))

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSInfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOct1 DosDevIOct2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD		KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek

<b>Family API</b>	
VIO	<a href="#">VioGetBuf</a> <a href="#">VioGetConfig</a> <a href="#">VioGetCurPos</a> <a href="#">VioGetCurType</a> <a href="#">VioGetPhysBuf</a> <a href="#">VioReadCellStr</a> <a href="#">VioReadCharStr</a> <a href="#">VioScrollUp</a> <a href="#">VioScrollDn</a> <a href="#">VioScrollLf</a> <a href="#">VioScrollRt</a> <a href="#">VioScrUnLock</a> <a href="#">VioSetCurPos</a> <a href="#">VioSetCurType</a> <a href="#">VioSetMode</a> <a href="#">VioGetMode</a> <a href="#">VioShowBuf</a> <a href="#">VioWrtCellStr</a> <a href="#">VioWrtCharStr</a> <a href="#">VioWrtCharStrAtt</a> <a href="#">VioWrtNAttr</a> <a href="#">VioWrtNCell</a> <a href="#">VioWrtNChar</a> <a href="#">VioWrtTTY</a> <a href="#">VioScrLock</a> <a href="#">VioPopUp</a>
Tools	BIND
Modules	<a href="#">DOSCALLS.DLL</a> <a href="#">VIOCALLS.DLL</a> <a href="#">KBDCALLS.DLL</a> <a href="#">MSG.DLL</a>
Libraries	<a href="#">API.LIB</a> <a href="#">OS2386.LIB</a> <a href="#">FAPI.LIB</a> <a href="#">DOSCALLS.LIB</a> <a href="#">SUBCALLS.LIB</a>

2018/08/25 15:05 · prokushev · [0 Comments](#)

From:  
<https://osfree.org./doku/> - **osFree wiki**

Permanent link:  
<https://osfree.org./doku/doku.php?id=en:docs:fapi:viowrttty&rev=1535799840>

Last update: **2018/09/01 11:04**

