

MouRemovePtr

Bindings: C, MASM

This call allows a process to notify the mouse device driver that the area defined by the passed parameters is for the exclusive use of the application. This area is defined as the collision area and is not available to the mouse device driver when drawing pointer images.

MouRemovePtr (PtrArea, DeviceHandle)

PtrArea (**PNOPTRRECT**) - input Address of the pointer shape collision area structure:

leftrow (**USHORT**) Upper left row coordinate (pels or characters).

leftcol (**USHORT**) Upper left column coordinate (pels or characters).

rightrow (**USHORT**) Lower right row coordinate (pels or characters).

rightcol (**USHORT**) Lower right column coordinate (pels or characters).

DeviceHandle (**HMOU**) - input Handle of the mouse device from a previous [MouOpen](#).

rc (**USHORT**) - return Return code descriptions are:

0	NO_ERROR
385	ERROR_MOUSE_NO_DEVICE
387	ERROR_MOUSE_INV_PARMS
466	ERROR_MOU_DETACHED
501	ERROR_MOUSE_NO_CONSOLE
505	ERROR_MOU_EXTENDED_SG

Remarks

[MouRemovePtr](#) may be issued by any process in the session. However, only one collision area is active at a time. Each [MouRemovePtr](#) command has the effect of resetting the collision area to the location and area specified by the current command.

If the logical pointer position is outside of the collision area specified by the latest [MouRemovePtr](#) command, the pointer image is drawn.

The [MouDrawPtr](#) command effectively cancels the [MouRemovePtr](#) command and allows the pointer to be drawn anywhere on the screen, until a new [MouRemovePtr](#) command is issued.

From:
<https://osfree.org/doku/> - **osFree wiki**

Permanent link:
<https://osfree.org/doku/doku.php?id=en:ibm:prcp:mou:removeptr&rev=1454565748>

Last update: **2016/02/04 06:02**

