

SVC_ERROREXIT

Terminate MVM with an error message. This call displays a message and then terminates the current MVM session.

Parameters

Register	Description
Stack (top)	Far pointer (segment:offset) to an ASCIIZ message string. The message is displayed by the host system before termination.

Return Value

This function does not return; it terminates the MVM.

Description

SVC_ERROREXIT provides a way to terminate the MVM (Multiple Virtual DOS Machine) with a user-supplied error message. It is specific to the OS/2 MVDM environment and has no direct equivalent in DOS INT 21h (the closest is AH=4Ch, which terminates without a message).

Before invoking the call, the far pointer (segment and offset) of a null-terminated ASCII string must be pushed onto the stack. The host system (OS/2) will display the message and then terminate the virtual machine.

Interface

```
/* SVC_ERROREXIT – terminate with error message (far pointer on stack) */  
extern void SvcErrorExit(const char far *msg);  
#pragma aux SvcErrorExit = \  
    "hlt"          \  
    "db 1"         \  
    "db NOT 1"    \  
    parm caller [] [msg] \  
    modify [ax bx cx dx];
```

Example

MASM

```
include macrolib.inc
```

```

push ds
push offset msg
@SvcErrorExit

msg db "Fatal error",0

```

C

```

#include <svc.h>

void main(void) {
    SvcErrorExit("Fatal error");
}

```

Notes

- The message string must be in the ASCIIZ format (zero-terminated).
- After this call, the MVM is terminated and control returns to the host operating system.
- Because the call never returns, no register values are preserved.

See Also

- [SVC_EXIT](#) - terminate without a message.
- [INT 21h AH=4Ch](#) - DOS terminate with return code.

SVC API	
Supervisor calls	0 1 2 3 4 5 6 7 8 9 10 11 12 13 14 15 16 17 18 19 20 21 22 23 24 25 26 27 28 29 30 31 32 33 34 35 36 37 38 39 40 41 42 43 44 45 46 47 48 49 50 51 52 53 54 55 56 57 58 59 60 61 62 63 64 65 66 67 68 69 70 71 72 73 74 75 76 77 78 79 80 81 82 83 84 85
Structures	FCB XFCB FILETIME FILEDATE

2024/11/07 03:44 · prokushev · [0 Comments](#)

From: <https://osfree.org/doku/> - **osFree wiki**

Permanent link: <https://osfree.org/doku/doku.php?id=en:docs:mvm:api:1&rev=1773975796>

Last update: **2026/03/20 03:03**

