



DosBeep

This call generates sound from the speaker.

Syntax

DosBeep (Frequency, Duration)

Parameters

- Frequency ([USHORT](#)) - input : Tone in Hertz (cycles per second) in the range 37 through 32767.
- Duration ([USHORT](#)) - input : Length of the sound in milliseconds.

Return Code

rc ([USHORT](#)) - return Return code descriptions are:

- 0 NO_ERROR
- 395 ERROR_INVALID_FREQUENCY

Remarks

DosBeep executes synchronously. An application program that invokes DosBeep waits until the specified number of milliseconds expire before it resumes execution.

Example Code

C Binding

```
#define INCL_DOSPROCESS

USHORT rc = DosBeep(Frequency, Duration);

USHORT Frequency;    /* Hertz (Hz) */
USHORT Duration;     /* Length of sound */

USHORT rc;           /* return code */
```

This example generates a beep for 1 second (1,000 milliseconds) at a frequency of 1,380.

```
#define INCL_DOSPROCESS
#define BEEP_FREQUENCY 1380
#define BEEP_DURATION 1000

USHORT rc;

rc = DosBeep(BEEP_FREQUENCY,
             BEEP_DURATION);
```

MASM Binding

```
EXTRN DosBeep:FAR
INCL_DOSPROCESS EQU 1

PUSH WORD Frequency ;Frequency (in Hertz)
PUSH WORD Duration ;Length of sound (in milliseconds)
CALL DosBeep
```

Returns WORD

Note

Text based on http://www.edm2.com/index.php/OS2_API:CPI:LEGACY:DosBeep

| Family API | | |
|------------|-----------------|--|
| DOS | Process Manager | DosBeep DosExit DosSleep DosExecPgm |
| | File Manager | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmDir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo DosShutdown |
| | Memory Manager | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias |
| | NLS | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage |
| | Date and Time | DosSetDateTime DosGetDateTime |
| | Devices | DosDevConfig DosDevIOctl DosDevIOctl2 |
| | Signals | DosHoldSignal DosSetSigHandler |
| KBD | Misc | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec |
| | | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek |

| Family API | |
|-------------------|---|
| VIO | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |
| Tools | BIND |
| Modules | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL |
| Libraries | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB |

2018/08/25 15:05 · [prokushev](#) · [0 Comments](#)

From:
<http://osfree.org/doku/> - **osFree wiki**

Permanent link:
<http://osfree.org/doku/doku.php?id=en:docs:fapi:dosbeep&rev=1607249911>

Last update: **2020/12/06 10:18**

