



**Note:** This IBM PC BIOS API call is for DOS/Win16 personality only. Use [Family API](#) for portability.

**Note:** [osFree Macro Library](#) provides macros for most of functions

2022/03/13 05:41 · prokushev · [0 Comments](#)

# Int 14H, AH=01H

## Version

IBM 5150 and higher

## Brief

Write character to port

## Family API

[DosWrite](#)

## Input

- AH = 00h
- AL = character to write
- DX = port number (00h-03h) (04h-43h for Digiboard XAPCM232.SYS)

## Return

- AH bit 7 clear if successful
- AH bit 7 set on error
- AH bits 6-0 = port status (see #00304)

## Macro

```
INCLUDE BIOS.INC
```

@AuxSendChar 0, 'A'

## Notes

- various network and serial-port drivers support the standard BIOS functions with interrupt-driven I/O instead of the BIOS's polled I/O
- the 1993/04/08 Compaq system ROM uses only the low two bits of DX

## Note

Text based on [Ralf Brown Interrupt List Release 61](#)

| <b>IBM PC BIOS API</b>      |  |
|-----------------------------|--|
| Video I/O                   | <b>INT 10H:</b> 00H, 01H, 02H, 03H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0CH, 0DH, 0EH, 0FH  |
| Hardware info               | <b>INT 11H, INT 12H</b>  |
| Serial I/O                  | <b>INT 14H:</b> 00H, 01H, 02H, 03H   |
| Tape I/O                    | <b>INT 15H:</b> 00H, 01H, 02H, 03H   |
| Keyboard I/O                | <b>INT 16H:</b> 00H, 01H, 02H  |
| Printer I/O                 | <b>INT 17H:</b> 00H, 01H, 02H  |
| Disk I/O                    | <b>INT 13H:</b> 00H, 01H, 02H, 03H, 04H, 05H   |
| Date and Time               | <b>INT 1AH:</b> 00H, 01H   |
| <b>osFree Macro Library</b> |  |
| Video I/O                   | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info               | @Equipment @MemSize  |
| Serial I/O                  | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus   |
| Tape I/O                    | @TapeOn @TapeOff @TapeRead @TapeWrite  |
| Keyboard I/O                | @KbdStatus @CharIn @CharPeek   |
| Printer I/O                 | @PrnPrint @PrnInit @PrnStatus  |
| Disk I/O                    | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat  |
| Date and Time               | @SetTime @GetTime  |
| Mouse                       | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion  |
| Memory manager              | @ModBlok SET_BLOCK   |

2022/10/04 14:28 · prokushev · [0 Comments](#)

2022/03/13 05:54 · prokushev · [0 Comments](#)

| Family API |   |  |
|------------|---|--|
| DOS        | Process Manager   | DosBeep DosExit DosSleep DosExecPgm  |
|            | File Manager  | DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo |
|            | Memory Manager  | DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias   |
|            | NLS   | DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage  |
|            | Date and Time   | DosSetDateTime DosGetDateTime  |
|            | Devices   | DosDevConfig DosDevIOct1 DosDevIOct2   |
|            | Signals   | DosHoldSignal DosSetSigHandler   |
|            | Misc  | BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec  |
| KBD        | KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek  |  |
| VIO        | VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp |  |
| Tools      | BIND  |  |
| Modules    | DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL  |  |
| Libraries  | API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB   |  |

2018/08/25 15:05 · prokushev · 0 Comments

From: <https://osfree.org./doku/> - osFree wiki

Permanent link: <https://osfree.org./doku/doku.php?id=en:docs:bios:api:int14:01&rev=1648302798>

Last update: 2022/03/26 13:53

