



This is part of **Family API** which allow to create dual-os version of program runs under OS/2 and DOS

Note: This is legacy API call. It is recommended to use 32-bit equivalent

2021/09/17 04:47 · prokushev · [0 Comments](#)

2021/08/20 03:18 · prokushev · [0 Comments](#)

This call returns the current ANSI status On/Off state.

Syntax

VioGetAnsi (Indicator, VioHandle)

Parameters

;Indicator (PUSHORT) - output : Address of the current ANSI status. A value of 1 indicates ANSI is active, and a value of 0 indicates ANSI is not active. ;VioHandle (HVIO) - input : This must be zero unless the caller is a Presentation Manager application, in which case it must be the value returned by VioGetPs.

Return Code

;rc (USHORT) - return:Return code descriptions are: * 0 NO_ERROR *436 ERROR_VIO_INVALID_HANDLE *465 ERROR_VIO_DETACHED

Bindings

C

```
<PRE> #define INCL_VIO
```

```
USHORT rc = VioGetAnsi(Indicator, VioHandle);
```

```
PUSHORT Indicator; /* On/Off indicator (returned) */ HVIO VioHandle; /* Vio handle */
```

```
USHORT rc; /* return code */ </PRE>
```

MASM

```
<PRE> EXTRN VioGetAnsi:FAR INCL_VIO EQU 1
```

```
PUSH@ WORD Indicator ;On/Off indicator (returned) PUSH WORD VioHandle ;Vio handle CALL
```

VioGetAnsi

Returns WORD </PRE>

Family API		
DOS	Process Manager	DosBeep DosExit DosSleep DosExecPgm
	File Manager	DosChDir DosChgFilePtr DosClose DosDelete DosDupHandle DosMkDir DosMove DosQCurDir DosQCurDisk DosSetFileMode DosOpen DosQFileInfo DosRead DosQFileMode DosQFSInfo DosQVerify DosRmdir DosSelectDisk DosFindClose DosFindFirst DosFindNext DosSetFileInfo DosSetVerify DosWrite DosFileLocks DosSetFHandState DosNewSize DosBufReset DosQFHandState DosSetFSinfo
	Memory Manager	DosFreeSeg DosSubAlloc DosSubFree DosSubSet DosAllocHuge DosAllocSeg DosReallocHuge DosReallocSeg DosGetHugeShift DosCreateCSAlias
	NLS	DosCaseMap DosGetCtryInfo DosGetDBCSEv DosSetCtryCode DosGetCollate DosGetMessage DosInsMessage DosPutMessage
	Date and Time	DosSetDateTime DosGetDateTime
	Devices	DosDevConfig DosDevIOctI DosDevIOctI2
	Signals	DosHoldSignal DosSetSigHandler
	Misc	BadDynLink DosGetEnv DosGetMachineMode DosGetVersion DosError DosErrClass DosSetVec
KBD	KbdCharIn KbdFlushBuffer KbdGetStatus KbdSetStatus KbdStringIn KbdPeek	
VIO	VioGetBuf VioGetConfig VioGetCurPos VioGetCurType VioGetPhysBuf VioReadCellStr VioReadCharStr VioScrollUp VioScrollDn VioScrollLf VioScrollRt VioScrUnLock VioSetCurPos VioSetCurType VioSetMode VioGetMode VioShowBuf VioWrtCellStr VioWrtCharStr VioWrtCharStrAtt VioWrtNAttr VioWrtNCell VioWrtNChar VioWrtTTY VioScrLock VioPopUp	
Tools	BIND	
Modules	DOSCALLS.DLL VIOCALLS.DLL KBDCALLS.DLL MSG.DLL	
Libraries	API.LIB OS2386.LIB FAPI.LIB DOSCALLS.LIB SUBCALLS.LIB	

2018/08/25 15:05 · prokushev · 0 Comments

From:

<https://osfree.org./doku/> - osFree wiki

Permanent link:

<https://osfree.org./doku/doku.php?id=en:docs:fapi:viogetansi&rev=1629450009>

Last update: 2021/08/20 09:00

