


**Note: This library for DOS/Win16 personality only. Use Family API for portability.**

**Note: osFree Macro Library provides macros for most of functions**

2022/04/10 06:34 · prokushev · 0 Comments

# @ModBlok

## Version

2.0+

## Brief

Modify memory block

## DOS Interrupt

INT21H: 4AH

## Family API

fapi

## Syntax

```
INCLUDE DOS.INC

@ModBlok PAR, SEGM
```

## Parameters

- PAR WORD New size in paragraphs
- SEGM WORD (optional) segment to change. IF not passed then ES used

# Return

- CF clear if successful
- CF set on error
  - AX = error code (07h,08h,09h) (see #01680 at AH=59h/BX=0000h)
  - BX = maximum paragraphs available for specified memory block

| **DOS API** | |
|---|---|
| Process manager | INT 20H, **INT 21H**: 00H, 25H, 26H, 31H, 34H, 35H, 4BH, 4CH, 4DH, 50H, 51H, 52H, 55H, 62H, INT 22H, INT 27H, INT 28H |
| File manager | INT 25H, INT 26H, **INT 21H**: 0DH, 0EH, 0FH, 10H, 11H, 12H, 13H, 14H, 15H, 16H, 17H, 19H, 1AH, 1BH, 1CH, 21H, 22H, 23H, 24H, 27H, 28H, 29H, 2EH, 2FH, 32H, 3305H, 36H, 39H, 3AH, 3BH, 3CH, 3DH, 3EH, 3FH, 40H, 41H, 42H, 4300H, 4301H, 45H, 45H, 46H, 4EH, 4FH, 54H, 56H, 5700H, 5701H, 5AH, 5BH, 5c00H, 5c01H, 60H, 67H, 68H, 6900H, 6901H, 6AH, 6CH |
| Character Device I/O | INT 29H, **INT 21H**: 01H, 02H, 03H, 04H, 05H, 06H, 07H, 08H, 09H, 0AH, 0BH, 0AH, 0CH, 5D07H, 5D08H, 5D09H, 5D0AH |
| Signals | INT 23H, INT 24H, **INT 21H**: 3300H, 3301H, 3302H |
| Memory manager | **INT 21H**: 48H, 49H, 4AH, 5800H, 5801H, 5802H, 5803H |
| Date and Time | **INT 21H**: 2AH, 2BH, 2CH, 2DH |
| Misc | **INT 21H**: 30H, 3306H, 3700H, 3701H, 3702H, 3703H, 59H |
| NLS | **INT 21H**: 3303H, 3304H, 3800H, 3801H, 6300H, 6301H, 6301H, 6500H, 6501H, 6502H, 6503H, 6504H, 6505H, 6506H, 6507H, 6520H, 6521H, 6522H, 6523H, 65A0H, 65A1H, 65A2H, 6601H, 6602H |
| Devices | **INT 21H**: 4400H, 4401H, 4402H, 4403H, 4404H, 4405H, 4406H, 4407H, 4408H, 4409H, 440AH, 440BH, 440CH, 440DH, 440EH, 440FH, 4410H, 4411H, 53H |
| Network | **INT 21H**: 5E00H, 5E01H, 5E02H, 5E03H, 5E04H, 5E05H, 5F00H, 5F01H, 5F02H, 5F03H, 5F04H, 5F05H, 5F07H, 5F08H |
| **osFree Macro Library** | |
| Video I/O | @SetMode @SetCurSz @SetCurPos @GetCur @SetPage @ScrollUp @ScrollDn @Scroll @GetChAtr @PutChAtr @PutCh @SetPalet @SetColor @SetDot @GetDot @WrtTTY @VideoState @GetMode @GetDisplay @GetVideoState @GetEGAInfo @Cls |
| Hardware info | @Equipment @MemSize |
| Serial I/O | @AuxInit @AuxSendChar @AuxRecieveChar @AuxStatus |
| Tape I/O | @TapeOn @TapeOff @TapeRead @TapeWrite |
| Keyboard I/O | @KbdStatus @CharIn @CharPeek |
| Printer I/O | @PrnPrint @PrnInit @PrnStatus |
| Disk I/O | @DskReset @DskStatus @DskRead @DskWrite @DskVerify @DskFormat |
| Date and Time | @SetTime @GetTime |
| Mouse | @MouInit @MouShowPointer @MouStatus @MouSetPos @MouSetMickey @MouRegion |
| Memory manager | @ModBlok SET_BLOCK |

2022/10/04 14:28 · prokushev · 0 Comments
2018/09/04 17:23 · prokushev · 0 Comments

From:
http://ftp.osfree.org/doku/ - **osFree wiki**

Permanent link:
**http://ftp.osfree.org/doku/doku.php?id=en:docs:macrolib:modblok**

Last update: **2022/10/09 02:54**